

---

# Internet for Guests

## Configure Autologon

1.0.0

English

Software Version V 2.8.280 or newer

21.07.2011



# Index

---

- 1. Introduction .....3
- 2. Configuration .....3

## 1. Introduction

---

The following information is required to configure Autologon devices manually:

- MAC Address of the Autologon device
- A free (unused) IP Address (e.g. 172.30.0.1)
- An explicit name for the device for identification
- Limits for the Autologon device:
  - Bandwidth (Upload and Download)
  - Data download limits (per session and per ticket)

Select, if PMS authentication is required to use the Autologon device.

## 2. Configuration

---

Therefore switch to the menu **Modules / Autologon Devices**. Here you can find the following configuration fields:

### New Device

IP Address: *	<input type="text"/>	Name: *	<input type="text"/>
MAC Address: *	<input type="text"/>	Description:	<input type="text"/>
Max Download Bandwidth:	Default <input type="text"/> kBit/s	Session Limit:	<input type="text"/> 200 MB
Max Upload Bandwidth:	Default <input type="text"/> kBit/s	Ticket Limit:	<input type="text"/> 200 MB
Activate:	<input checked="" type="checkbox"/>	PMS Authentication:	<input type="checkbox"/>
New DHCP Static Lease:	<input checked="" type="checkbox"/>		
<input type="button" value="Save"/>			

Now enter the information you gathered at point 1 (Introduction):

- **IP Address**  
Enter the desired IP Address here.
- **MAC Address**  
Enter the MAC Address of the Autologon device
- **Max Download / Upload Bandwidth**  
The standard settings here are the same settings as in menu **Settings / Network (Bandwidth Management)**.
- **Activate**  
Check “Activate” to enable this Autologon device.

- **New DHCP Static Lease**  
If checked, the Autologon device gets a static IP Address from the DHCP Service. Activating Static Lease for Autologon devices is highly recommended.
- **Name**  
Enter an explicit name of the device for identification.
- **Description**  
Enter a description for the device (e.g. place where the system is located).
- **Session Limit**  
Defines the Download and Upload volume in Megabyte the user gets per Session (e.g. 50 MB). This can be used to prevent users from downloading big files. The user will be disconnected automatically if he reaches the Session Limit and has to re-logon.
- **Ticket Limit**  
Defines the Download and Upload volume in Megabyte the user gets per Ticket (e.g. 100 MB). The user will be disconnected automatically and the ticket get invalid if Ticket Limit is reached.
- **PMS Authentication**  
Defines whether the user must authenticate via PMS to logon using this Autologon device. No booking record will be send to PMS.

After saving the settings, you have to restart the Autologon Service for changes to take effect.